QTDISPLAYSPEC.PY DOCUMENTATION

MICHAEL TOPPING

1. Classes

spectrumClass.

init.

• Paremeters:

- loc directory that the spectrum is in.
- filename filename of the spectrum file.
- emRedshift guess for the redshift based on emission features.
- absRedshift guess for the redshift based on absorption features.
- aperture the aperture in the fits file that the object spectrum is in.
- Description: This procedure will open the data file and set member variables spec and wavelengths to the appropriate values. If there are more than one aperture in the file, the aperture that contains the object needs to be specified. When creating the wavelengths array, the wavelengths solution is pulled from the fits header. If no information on the wavelengths solution is available, a default is used that may be incorrect for the current file. We are only looking at $\text{Ly}\alpha$ as z=3 so we cut down the range of the spectrum. Then we call a function to create a smoothed version of the spectrum.

getSmoothedSpectrum.

• Paremeters:

smoothFac - number of points that will be used to calculate median for smoothing, must be an odd number.

• Description: First the current spectrum is smoothed by taking the median of each smoothFac number of points. Then it is fit to a spline and interpolated to match the number of data points of the original spectrum.

remove Spec.

- Parameters:
 - center center wavelength of the line that you want removed.
- Description: Used to take out sky lines that will confuse the code. Input the wavelength of the line and it will be replaced by the "continuum" of the spectrum.

findRms.

- Paremeters:
 - rmsThresh the amount above the continuum that a datapoint must be for the code to declare it an emission feature.
- Description: This is what finds the lines. If the noise is not constant through the entire spectrum this will split it up and check different parts of the spectrum separately. First the rms value of the spectrum is calculated, then anything that is rmsThresh times that will be picked out as a possible line and added to the peaks member variable.

remove Dup Peaks.

• Description: The findRms function picks out every data point that is above the threshold and adds it to the list of peaks. In some cases more than one data point in a single spectral line will be added to the list. If this happens, the central one is kept in the list of peaks, and the others are removed. Otherwise, the same emission line could be fit more than once.

fitline.

- Paremeters:
 - peak the index of the peak that you want to fit to a gaussian.

- plotBool boolean, whether you want the procedure to create and save plots of the fits.
- Description: This is the function that fits the emission lines to a gaussian. Given an initial guess for the center of the emission line, the points ±10 from the peak (roughly 15Å) are picked out and set to the subSpectra and subWavelengths variables. Then we make a check to see if the line is right on the edge of the spectrum, which would cause some problems. Then the line is fit to a gaussian function using scipy curve_fit function.

If the plotBool variable is true, a plot of the full spectrum and a zoom in of the line with its fit is saved as a .png.

datasetClass.

init.

- Parameters
 - folder the directory name for the list of spectrum
 - listFile the name of the file that list the spectrum
- Optional Parameters
 - usecols=() the columns that will be read in from the spectrum list file.
- Description: A dataset object requires a file that contains a list of spectra filenames. It will read in this file and keep track of all the filenames in the dataset. The optional keyword argument is used if there are multiple columns in the file, e.g. redshift data, or notes. This object also contains one spectrum object at a time, and is initialized to the first spectrum in the list.

setSpectrum.

- Parameters
 - index the index of the current spectrum
- Description: Changes the member spectrum object to a different one. It will use the indexth one in the list of spectra.

2. Application (QtDisplaySpec.py)

PlotCanvas. This class extends the FigureCanvas class. It doesn't really do much, just sets some parameters of the plot.

DynamicPlotCanvas. Extends PlotCanvas. This is where the spectrum is plotted. The input is a spectrum class object.

update_figure. This is called every frame. It clears the current axes, and plots the spectrum in the plotting window. If emission lines have been found, it will plot their locations as well.

ApplicationWindow. Extends QMainWindow. This is what controls the application.

init. This is where the list of dataset object is created. Once created, the current spectrum is set to the first spectrum in the first dataset. We also want the application to do something so we will create the button objects as member variables. Then we add the buttons and the plotting window to the layout of the application. Finally, we connect all the buttons to check if they are clicked. If they are clicked then a procedure is called.

fileQuit. Quits the application

closeEvent. Calls the fileQuit procedure which closes the application.

findLines. Calls the spectrum class findRms function to detect all of the lines, then removes duplicates.

findZ. This finds the redshift of the current spectrum. If findLines has not been called yet, so lines have not been found, then that procedure is called. Then it looks for the strongest line, fits it to a gaussian, and assumes that it is $Ly\alpha$, and can calculate the redshift from that.

findAllZ. This will run through all of the spectra in all of the datasets and create a list of all of their redshifts. It runs through the same procedure that findZ goes through to detect emission lines and calculate their redshift from that. If the emission lines are too difficult for the code to pick out of the spectrum and a guess redshift is available, the code then will take the line corresponding to $Ly\alpha$ at that redshift, and fit a gaussian to it, then returns the center of that line as the new redshift. If the code cannot find any lines, and no emission guess redshift is provided, but there is an absorption guess redshift, it will cross correlate the spectrum with a list of metal absorption lines to find the most likely redshift. Then a histogram is created from the list of redshifts.

cycleDataSet. This will cycle through all of the datasets that are in the list of datasets.

prevSpec. Moves to the previous spectrum in the list.

nextSpec. Moves to the next spectrum in the list.

loadData. Opens up a file browser to select more data to analyze. It is currently not finished.